

NAME

pdftex, pdfninitex, pdfvirtex – PDF output from TeX

SYNOPSIS

pdftex [*options*] [**&format**] [*file*|*commands*]

DESCRIPTION

Run the pdf_T_EX typesetter on *file*, usually creating *file.pdf*. If the file argument has no extension, ".tex" will be appended to it. Instead of a filename, a set of pdf_T_EX commands can be given, the first of which must start with a backslash. With a **&format** argument pdf_T_EX uses a different set of precompiled commands, contained in *format.fmt*; it is usually better to use the **-fmt** *format* option instead.

pdf_T_EX is a version of _T_EX, with the e-_T_EX extensions, that can create *PDF* files as well as *DVI* files.

In *DVI* mode, pdf_T_EX can be used as a complete replacement for the _T_EX engine.

The typical use of pdf_T_EX is with a pregenerated formats for which PDF output has been enabled. The **pdftex** command uses the equivalent of the plain _T_EX format, and the **pdflatex** command uses the equivalent of the L^A_T_EX format. To generate formats, use the **-ini** switch.

The **pdfninitex** and **pdfvirtex** commands are pdf_T_EX's analogues to the **initex** and **virtex** commands. In this installation, if the links exist, they are symbolic links to the **pdftex** executable.

In *PDF* mode, pdf_T_EX can natively handle the *PDF*, *JPG*, *JBIG2*, and *PNG* graphics formats. pdf_T_EX cannot include PostScript or Encapsulated PostScript (EPS) graphics files; first convert them to PDF using **epstopdf**(1). pdf_T_EX's handling of its command-line arguments is similar to that of the other _T_EX programs in the *web2c* implementation.

OPTIONS

This version of pdf_T_EX understands the following command line options.

-draftmode

Sets \pdfdraftmode so pdf_T_EX doesn't write a PDF and doesn't read any included images, thus speeding up execution.

-enc Enable the enc_T_EX extensions. This option is only effective in combination with **-ini**. For documentation of the enc_T_EX extensions see <http://www.olsak.net/encTex.html>.

-etex Enable the e-_T_EX extensions. This option is only effective in combination with **-ini**. See **etex**(1).

-file-line-error

Print error messages in the form *file:line:error* which is similar to the way many compilers format them.

-no-file-line-error

Disable printing error messages in the *file:line:error* style.

-file-line-error-style

This is the old name of the **-file-line-error** option.

-fmt *format*

Use *format* as the name of the format to be used, instead of the name by which pdf_T_EX was called or a %& line.

-halt-on-error

Exit with an error code when an error is encountered during processing.

-help Print help message and exit.**-ini** Start in *INI* mode, which is used to dump formats. The *INI* mode can be used for type-setting, but no format is preloaded, and basic initializations like setting catcodes may be required.**-interaction** *mode*

Sets the interaction mode. The mode can be either *batchmode*, *nonstopmode*, *scrollmode*, and *errorstopmode*. The meaning of these modes is the same as that of the corresponding `\commands`.

-ipc Send DVI or PDF output to a socket as well as the usual output file. Whether this option is available is the choice of the installer.**-ipc-start**

As **-ipc**, and starts the server at the other end as well. Whether this option is available is the choice of the installer.

-jobname *name*

Use *name* for the job name, instead of deriving it from the name of the input file.

-kpathsea-debug *bitmask*

Sets path searching debugging flags according to the bitmask. See the *Kpathsea* manual for details.

-mktex *fnt*

Enable `mktex fnt`, where *fnt* must be either *tex* or *tfm*.

-mltex Enable ML \TeX extensions. Only effective in combination with **-ini**.**-no-mktex** *fnt*

Disable `mktex fnt`, where *fnt* must be either *tex* or *tfm*.

-output-comment *string*

In *DVI* mode, use *string* for the *DVI* file comment instead of the date. This option is ignored in *PDF* mode.

-output-directory *directory*

Write output files in *directory* instead of the current directory. Look up input files in *directory* first, then along the normal search path.

-output-format *format*

Set the output format mode, where *format* must be either *pdf* or *dvi*. This also influences the set of graphics formats understood by pdf \TeX .

-parse-first-line

If the first line of the main input file begins with `%&` parse it to look for a dump name or a **-translate-file** option.

-no-parse-first-line

Disable parsing of the first line of the main input file.

-progname *name*

Pretend to be program *name*. This affects both the format used and the search paths.

-recorder

Enable the filename recorder. This leaves a trace of the files opened for input and output in a file with extension *.fls*.

-shell-escape

Enable the `\write18{command}` construct. The *command* can be any shell command. This construct is normally disallowed for security reasons.

-no-shell-escape

Disable the `\write18{command}` construct, even if it is enabled in the *texmf.cnf* file.

-src-specials

In *DVI* mode, insert source specials into the *DVI* file. This option is ignored in *PDF* mode.

-src-specials where

In *DVI* mode, insert source specials in certain places of the *DVI* file. *where* is a comma-separated value list: *cr*, *display*, *hbox*, *math*, *par*, *parent*, or *vbox*. This option is ignored in *PDF* mode.

-translate-file tcxname

Use the *tcxname* translation table to set the mapping of input characters and re-mapping of output characters.

-default-translate-file tcxname

Like **-translate-file** except that a `%&` line can overrule this setting.

-version

Print version information and exit.

ENVIRONMENT

See the Kpathsearch library documentation (the ‘Path specifications’ node) for precise details of how the environment variables are used. The **kpsewhich** utility can be used to query the values of the variables.

One caveat: In most pdf_TE_X formats, you cannot use `~` in a filename you give directly to pdf_TE_X, because `~` is an active character, and hence is expanded, not taken as part of the filename. Other programs, such as METAFONT, do not have this problem.

TEXMFOUTPUT

Normally, pdf_TE_X puts its output files in the current directory. If any output file cannot be opened there, it tries to open it in the directory specified in the environment variable **TEXMFOUTPUT**. There is no default value for that variable. For example, if you say *pdf_TE_X paper* and the current directory is not writable and **TEXMFOUTPUT** has the value */tmp*, pdf_TE_X attempts to create */tmp/paper.log* (and */tmp/paper.pdf*, if any output is produced.) **TEXMFOUTPUT** is also checked for input files, as _TE_X often generates files that need to be subsequently read; for input, no suffixes (such as “.tex”) are added by default, the input name is simply checked as given.

TEXINPUTS

Search path for `\input` and `\openin` files. This should start with “.”, so that user files are found before system files. An empty path component will be replaced with the paths defined in the *texmf.cnf* file. For example, set **TEXINPUTS** to “.:/home/user/tex:” to prepend the current directory and “/home/user/tex” to the standard search path.

TEXFORMATS

Search path for format files.

TEXPOOL

search path for **pdf_ftex** internal strings.

TEXEDIT

Command template for switching to editor. The default, usually **vi**, is set when pdf_fT_EX is compiled.

TFMFORMATS

Search path for font metric (*.tfm*) files.

FILES

The location of the files mentioned below varies from system to system. Use the **kpsewhich** utility to find their locations.

pdf_ftex.pool

Text file containing pdf_fT_EX's internal strings.

pdf_ftex.map

Filename mapping definitions.

**.tfm* Metric files for pdf_fT_EX's fonts.

**.fmt* Predigested pdf_fT_EX format (*.fmt*) files.

NOTES

Starting with version 1.40, pdf_fT_EX incorporates the e-T_EX extensions, and pdf_eT_EX is just a copy of pdf_fT_EX. See **etex**(1). This manual page is not meant to be exhaustive. The complete documentation for this version of pdf_fT_EX can be found in the *pdf_fT_EX manual* and the info manual *Web2C: A TeX implementation*.

BUGS

This version of pdf_fT_EX implements a number of optional extensions. In fact, many of these extensions conflict to a greater or lesser extent with the definition of pdf_fT_EX. When such extensions are enabled, the banner printed when pdf_fT_EX starts is changed to print **pdf_fTeXk** instead of **pdf_fTeX**.

This version of pdf_fT_EX fails to trap arithmetic overflow when dimensions are added or subtracted. Cases where this occurs are rare, but when it does the generated *DVI* file will be invalid. Whether a generated *PDF* file would be usable is unknown.

AVAILABILITY

pdf_fT_EX is available for a large variety of machine architectures and operation systems. pdf_fT_EX is part of all major T_EX distributions.

Information on how to get pdf_fT_EX and related information is available at the **<http://www.pdf-tex.org>** pdf_fT_EX web site.

The following pdf_eT_EX related mailing list is available: **pdf_ftex@tug.org**. This is a mailman list; to subscribe send a message containing *subscribe* to **pdf_ftex-request@tug.org**. A web interface and list archives can be found at the **<http://lists.tug.org/pdf_ftex>** mailing list web site.

SEE ALSO

epstopdf(1), **etex**(1), **latex**(1), **mptopdf**(1), **tex**(1), **mf**(1). <http://tug.org/applications/pdf_ftex>, <http://tug.org/web2c>.

AUTHORS

The primary authors of pdf \TeX are Han The Thanh, Petr Sojka, Jiri Zlatuska, and Peter Breitenlohner (e \TeX).

\TeX was designed by Donald E. Knuth, who implemented it using his WEB system for Pascal programs. It was ported to Unix at Stanford by Howard Trickey, and at Cornell by Pavel Curtis. The version now offered with the Unix \TeX distribution is that generated by the WEB to C system (**web2c**), originally written by Tomas Rokicki and Tim Morgan.

The enc \TeX extensions were written by Petr Olsak.